

LPARDesign

USER'S GUIDE

Version V11-T01



Doc : LPARDesign-HD-zPCR-V11-T01_UserGuide.docx
 © 2020 IBM Corporation
 Updated: May 12th, 2020

Alain Maneville
 Executive I/T Specialist, zChampion
 z Client Architect
 France

Table Of Content

1. PURPOSE OF THE DOCUMENT.....	3		
2. DISCLAIMER OF WARRANTIES:.....	3		
3. ACKNOWLEDGEMENTS:.....	3		
4. HOW TO GET THE PRODUCT – IMPORTANT NOTICE:.....	4		
4.1 FROM THE IBM WLM WEB SITE (AS OF OCTOBER 2018).....	4		
4.2 FROM GITHUB	4		
5. CHANGES IN THIS RELEASE.....	5		
5.1 WHAT'S NEW IN V11T01.....	5		
5.1.1 Support for z15-T02 (8562).....	5		
5.1.2 Support for zPCR 9.4	5		
5.1.3 Support of ICF configuration (standalone definition or imported from zPCR)	5		
5.1.4 Dashboard environment Enhancement	5		
5.1.5 Task Bar Enhancement.....	5		
5.1.6 XML file creation for comparison purpose	5		
5.2 WHAT'S NEW IN V10T01?.....	5		
5.2.1 Support of the new IBM Z - z15 (machine type 8561).....	5		
5.2.2 New way of acquiring the tool.....	5		
5.2.3 Support of zPCR 9.3	5		
5.2.4 Export LPARDdesign study in XML format for COMPARE purpose.	5		
5.2.5 EXPERT recommendations accuracy	6		
6. THE NAVIGATION AND ACTION BAR.....	7		
6.1 BAR FUNCTIONS.....	7		
7. MANAGEMENT OF MESSAGES.....	8		
8. A BRIEF VIEW OF THE SPREADSHEET.....	9		
8.1 THE START WORKSHEET:.....	9		
8.2 THE CONFIG WORKSHEET:	9		
8.3 THE CONFIG-MSU WORKSHEET:	9		
8.4 THE CONFIG-ZXXP WORKSHEET:.....	10		
8.5 THE CONFIG-IFL WORKSHEET:	10		
8.6 THE CONFIG-ICF WORKSHEET:.....	10		
8.7 THE EXPERT WORKSHEET:	10		
8.8 THE SYNTHESIS WORKSHEET:.....	10		
8.9 THE DASHBOARD WORKSHEET.....	11		
8.10 THE TABLES AND SINET WORKSHEETS.....	11		
9. SPREADSHEET USAGE.....	12		
9.1 START SPREADSHEET USAGE	12		
9.1.1 Specifying the Machine type (GCP) and/or #zIIP and/or #IFL and/or ICF.....	12		
9.1.2 Accept SPECIAL ConF? YES or NO.....	12		
9.1.3 Set / Change the Configuration for GCP, zIIP, ICF and IFL.....	13		
9.1.3.1 Notes on LinuxONE machine support	14		
9.1.4 Always keep a fresh copy of the initial spreadsheet.....	14		
9.2 CONFIG SPREADSHEET USAGE.....	15		
9.2.1 Define the basic LPAR GCP configuration.....	15		
9.2.2 Validating the configuration – with <table border="1" style="display: inline-table; vertical-align: middle;"><tr><td style="padding: 2px 10px;">Accept SPECIAL ConF ?</td><td style="padding: 2px 10px; background-color: green; color: white;">NO</td></tr></table>	Accept SPECIAL ConF ?	NO	15
Accept SPECIAL ConF ?	NO		
9.2.3 Validating the configuration – with: <table border="1" style="display: inline-table; vertical-align: middle;"><tr><td style="padding: 2px 10px;">Accept SPECIAL ConF ?</td><td style="padding: 2px 10px; background-color: red; color: white;">YES</td></tr></table>	Accept SPECIAL ConF ?	YES	16
Accept SPECIAL ConF ?	YES		
9.2.4 Sorting selected columns.....	17		
9.2.5 Explanation of some columns.....	18		
9.2.6 Computing the HiperDispatch® number of LPs.....	19		



9.2.7	<i>Linking to zPCR</i>	20
9.2.8	<i>Deleting LPARs</i>	21
9.3	CONFIG-MSU SPREADSHEET USAGE	22
9.3.1	<i>General usage notice</i> :	22
9.3.2	<i>LPAR and Capacity Definitions</i>	22
9.3.3	<i>Group Calculation</i>	23
9.3.4	<i>Other buttons functions</i> :	24
9.3.5	<i>Explanation of this tab header</i> :	24
9.4	CONFIG-ZXXP SPREADSHEET USAGE	25
9.4.1	<i>Only zIIP are supported in this release</i>	25
9.4.2	<i>Support for Special Configuration for zIIPs</i> :	27
9.5	THE CONFIG-IFL SPREADSHEET USAGE	28
9.5.1	<i>Sorting selected columns</i>	29
9.6	THE CONFIG-ICF SPREADSHEET USAGE	30
9.6.1	<i>Sorting selected columns</i>	30
9.7	SYNTHESIS SPREADSHEET USAGE	31
9.8	EXPERT SPREADSHEET USAGE	32
9.8.1	<i>EXPERT Notes for GCP</i>	32
9.8.1.1	The rules used for advices in GCP:	32
9.9	EXPERT NOTES FOR ZIIPs	34
9.10	EXPERT NOTES FOR IFL	34
9.11	DASHBOARD SPREADSHEET USAGE	35
9.11.1	<i>DASHBOARD for zIIP enhancement</i>	36
10.	LINK WITH ZPCR.....	37
10.1	GENERAL CONSIDERATIONS ON THIS FEATURE	37
10.2	CURRENT LIMITATIONS OF THE LINK TO ZPCR FEATURE	37
10.2.1	<i>Specifying an LPAR with unsufficient number of LPs to sustain the share</i>	37
10.2.2	<i>Processors type</i>	37
10.2.3	<i>Reference CPU</i>	37
10.2.4	<i>zPCR Version</i>	37
10.2.5	<i>z/OS Version</i>	38
10.3	USING THE ZPCR EXPORT FEATURE	38
10.4	USING THE ZPCR IMPORT FEATURE	40
11.	PRINTING THE SHEETS	41
12.	FAQ, COMMON MISTAKES AND RELEASE RECOMMENDATIONS	42
12.1	FAQ	42
12.2	COMMON MISTAKES	44
12.3	RELEASE RECOMMENDATIONS:	45
13.	RECOMMENDED USAGE WORKFLOW	46



1. PURPOSE OF THE DOCUMENT.

This document explains how to use the LPARDdesign Tool.

This tool helps in configuring LPARs for all processor type (HiperDispatch® eligible).

It provides the calculation of the number of HighShare, MediumShare and LowShare LPs when HiperDispatch® is available on the studied machine.

2. DISCLAIMER OF WARRANTIES:

The following [enclosed] macro is sample code created by Alain Maneville - IBM France.

This sample macro is not part of any standard IBM product and is provided to you solely for assisting you in the PR/SM LPAR Configuration

The code is provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of such sample code, even if you have been advised of the possibility of such damage

Support: Support will be provided on a "best effort" basis. Send the spreadsheet for an analysis to alain_maneville@fr.ibm.com

3. ACKNOWLEDGEMENTS:

I would like to thank the following people for their help and contribution to this worksheet

Thierry DELERIS – A customer from BPCE-IT (France).

He wrote the code of the DASHBOARD worksheet and did a great job for the zPCR link feature, the Task bar and more!.

Robert VAUPEL - STSM, z/OS Workload and Performance Management.

He helped me understand the HiperDispatch® Algorithms and LP spread in VH, VM and VL.

The new worksheet CONFIG-MSU comes from him.



4. HOW TO GET THE PRODUCT – IMPORTANT NOTICE:

4.1 From the IBM WLM WEB Site (as of October 2018)

<https://www.ibm.com/it-infrastructure/z/zos-workload-management>

Go down to this section (skip the Featured products and More products sections)

Popular links	WLMQUE tool	LPAR design tool	Reporting tools
FAQs	The WLM Work Queue Viewer (WLMQUE) is a small ISPF-based tool to assist in displaying the application environments that are currently being used on your z/OS system.	The LPAR design tool assists you in planning the LPAR layout of your Central Processor Complexes.	The topology report displays logical processor topology and the SMF 113 reporting tool provides insight into usage of cache structures.
Guides			Download topology report (EXE, 1.13 KB)
Redbooks			Download SMF 113 reporting (EXE, 6.2 MB)
Tools for WLM			
Tools for RMF			

[Download LPAR design tool \(ZIP, 2.2 MB\)](#)

And click on

4.2 From Github

Due to a change in IBM's way of managing WEB sites, the product is now available on the GitHub Web site at the URL:

<https://github.com/AlainManeville/z-OS-LPARDesign>

You will get this page :

LPARDDesign Tool - Helps in configuring your CPC for PR/SM and HiperDispatch

22 commits	1 branch	0 packages	0 releases	1 contributor
Branch: master	New pull request	Find file	Clone or download	
AlainManeville Add files via upload		Latest commit 2d6b045 on Jan 13		
LPARDDesign-HD-zPCR-V10-T01_IBM.xls	Add files via upload	4 months ago		
LPARDDesign-HD-zPCR-V10-T01_UserGuide.pdf	Add files via upload	4 months ago		
README.md	Update README.md	8 months ago		

Then, Click on the LPAR Design Hyperlink for the spreadsheet **AND** the User's Guide to download them.



5. CHANGES IN THIS RELEASE.

5.1 What's new in V11T01

The V11-T01 version is a major redesign of the tool.

5.1.1 Support for z15-T02 (8562)

The z15-T02 (8561) is supported in this release

5.1.2 Support for zPCR 9.4

zPCR 9.4 is supported in this release

5.1.3 Support of ICF configuration (standalone definition or imported from zPCR)

The ICF configuration is now imported or exported to/from zPCR.

This will make the link to and from zPCR totally transparent as the ICF (even not HD eligible) are now included.

5.1.4 Dashboard environment Enhancement

When LPAR have DED LPs the color has been changed in dark green

When LPAR do not have zIIP allocation, the color has been changed to dark grey

ICF is now included in the Dashboard

5.1.5 Task Bar Enhancement

The Task Bar includes the ICF buttons

The Task Bar includes the XML menu which is now operative

5.1.6 XML file creation for comparison purpose

This was a long-time request. You can now save your LPARDdesign studies and load them in a new spreadsheet – LPARDdesign Extended to compare the configurations.

LPARDdesign Extended is a companion Tool and has its own macro and User's Guide.

5.2 What's new in V10T01?

5.2.1 Support of the new IBM Z - z15 (machine type 8561)

The machine type 8561, the new z15 is supported in this release.

5.2.2 New way of acquiring the tool.

See chapter 4 for this new way.

5.2.3 Support of zPCR 9.3

zPCR 9.3 is now supported in this version.

5.2.4 Export LPARDdesign study in XML format for COMPARE purpose.



This is for future use. It will help comparing various flavors of the configuration.

5.2.5 EXPERT recommendations accuracy


The Guaranteed number of Physical Processors has been enhanced for more accuracy in having 3 digits after the coma. This improve the accuracy of the EXPERT recommendations when computing the recommended new Weight.



6. THE NAVIGATION AND ACTION BAR.

To make things simpler and easier, a new navigation and action BAR is provided. It is available when you open the spreadsheet and stays until you close it. You can move it anywhere in the worksheets (you will do that when first opening the product).

6.1 BAR Functions.



It is now easier when you are in a particular PU configuration to view the EXPERT or the DASHBOARD. At any time, you can see your general configuration, validate it and check it.


Again, any change in the number of PU must be done in the START worksheet!

Sliding the mouse pointer to one of the icons shows its function:



7. MANAGEMENT OF MESSAGES.

All the messages (validation, error and so on) will be now displayed in a single box.
This prevent to have to click "OK" after each message.
An example is given in this picture:



At any time, you can review these messages for a particular PU type by clicking on the  Icon.



8. A BRIEF VIEW OF THE SPREADSHEET.

The spreadsheet is now composed of 9 worksheets:

START | CONFIG | CONFIG-zXXP | CONFIG-IFL | CONFIG-ICF | CONFIG-MSU | EXPERT | SYNTHESIS | DASHBOARD.

8.1 The START worksheet:

This worksheet is opened automatically when you start the workbook.

You must use it to set the number of GCP, zIIP and IFL and to set your “special configurations” parameter. Then you can specify a “Study ID” that will be used in the spreadsheet or in the zPCR study.

The only way to change the value of GCP, zIIP and IFL is to go back to the START worksheet.

You can go to this START worksheet by clicking on the  button on the navigation Bar.

A check of a mix of these processors will be done before you can go to the various LPAR Definition.

Other functions provided are:

- Create a copy (so you can always have a basic version of the tool)
- Save as (to save your work)
- The navigation Bar will let you go to other functions for this particular PU or to other functions..

8.2 The CONFIG worksheet:

This worksheet helps you define:

- The LPARs characteristics for the GCP (as you would do on the HMC)
- Validation of the LPAR configuration and Calculation of the HiperDispatch® processor in HighShare, MediumShare and LowShare LPs using the navigation Bar  icon.
- Note : The Machine type and model are now changed only in the START worksheet.

Other functions provided are:

- Delete LPAR(s)
- Create a .zPCR study file or update an LPARDdesign spreadsheet with an existing .zPCR study file.
- The navigation Bar will let you go to other functions for this particular PU or to other functions.
- Sorting (ascending and descending) of selected columns.

8.3 The CONFIG-MSU worksheet:

This worksheet helps you define:

- The DEFINED CAPACITY values for a single LPAR.
- A GROUP CAPACITY value for a set of LPARs.

The calculations and information provided are explained in the spreadsheet usage section specific to this spreadsheet.



8.4 The CONFIG-ZXXP worksheet:

This worksheet helps you define:

- The LPARs characteristics for the zIIP (as you would do on the HMC).

Other functions provided are in the navigation BAR:



8.5 The CONFIG-IFL worksheet:

This worksheet helps you define:

- The LPARs characteristics for the IFL (as you would do on the HMC).

Other functions provided are in the navigation BAR:



8.6 The CONFIG-ICF worksheet:

This worksheet helps you define:

- The LPARs characteristics for the ICF (as you would do on the HMC).
- Note: ICF are not eligible PU for HiperDispatch® - this configuration is there to fully support a zPCR study

Other functions provided are in the navigation BAR:



8.7 The EXPERT worksheet:

This worksheet might help you optimizing your current configuration for:

- GCP, zIIP and IFL.

You choose the EXPERT recommendations you want by clicking on the appropriate button on the top of the worksheet or directly in the navigation BAR.

[Click for EXPERT NOTES - GCP](#)

[Click for EXPERT NOTES - zIIP](#)

[Click for EXPERT NOTES - IFL](#)

8.8 The SYNTHESIS worksheet:

This worksheet shows the HiperDispatch® effects for the GCP, zIIP and IFL.




8.9 The DASHBOARD worksheet

This worksheet provides a view of the processor layout for:

- GCP, zIIP, IFL and ICF.

You choose the DASHBOARD you want by clicking on the appropriate button on the top of the worksheet or directly  in the navigation BAR.



8.10 The Tables and SINET worksheets.

These are management worksheets. **Do not alter them!**



9. SPREADSHEET USAGE.

**ONLY CELLS IN YELLOW SHOULD BE FILLED.
USE THE navigation BAR TO NAVIGATE WITHIN WORKSHEETS.
CONFIGURATION DATA MUST BE CHANGED IN THE START WORKSHEET**

When you open the workbook, you are automatically directed to the START worksheet. Important changes have been done in this release, the START worksheet is now the only place to change the configuration of the PU. The navigation BAR is displayed too. You can move it anywhere if needed.

9.1 START SPREADSHEET Usage.

This macro evaluates the LPAR definition for HD eligible processors												
To create a copy of this spreadsheet	Create a copy...	Optional but recommended										
<div style="display: flex; align-items: center; justify-content: space-between;"> <div style="flex: 1;">  <p style="margin-top: 10px;">To start</p> <p style="margin-top: 10px;">Accept SPECIAL ConF ? YES</p> </div> <div style="flex: 1; text-align: right;"> <p style="margin-top: 10px;">Change Customer Name / ID</p> <table border="1" style="width: 100%; border-collapse: collapse; text-align: center;"> <thead> <tr> <th colspan="2" style="background-color: #ffffcc;">2 - Change Configuration</th> </tr> </thead> <tbody> <tr> <td>Machine-Type</td> <td>8561-718</td> </tr> <tr> <td>#zIIP</td> <td>18</td> </tr> <tr> <td>#ICF</td> <td>18</td> </tr> <tr> <td>#IFL</td> <td>18</td> </tr> </tbody> </table> <p style="margin-top: 10px; color: green;">==> Not HD Eligible</p> </div> </div>			2 - Change Configuration		Machine-Type	8561-718	#zIIP	18	#ICF	18	#IFL	18
2 - Change Configuration												
Machine-Type	8561-718											
#zIIP	18											
#ICF	18											
#IFL	18											
To save results	=====>	Save as...										

You can specify an identification of your study that will be set in the ID= field of the various titles. You can change it using the **Change Customer Name / ID** button. The LPARDesign version and the current zPCR version are displayed in the first row of the sheet.

9.1.1 Specifying the Machine type (GCP) and/or #zIIP and/or #IFL and/or ICF.

This is now the place you do these specifications. If you want to change them, you must go back to this spreadsheet by clicking on the **Go To Start** button on the navigation BAR.

9.1.2 Accept SPECIAL ConF? YES or NO.

Accept SPECIAL ConF ? NO

PR/SM accepts configurations where the number of the HMC defined LPs is not consistent with the number of LPs needed to sustain the share of the LPAR.

This might happen in some Ksys GDPS LPAR configuration or if the customer defines "White Space" LPARs.

To inform the process that you will accept special configurations, just say YES in the proposed choices. The effects of saying "YES" will be explained in the CONFIG sheet usage. To run with the regular process, say "NO".



9.1.3 Set / Change the Configuration for GCP, zIIP, ICF and IFL

You can now specify all the full configuration in terms of Machine-Type (GCPs), zIIPs and IFLs. Some validations are done to check the health of these settings (for example, do not specify zIIPs for an IFL only machine).

The following cells should be filled:

2 - Change Configuration	
Machine-Type	8561-718
#zIIP	18
#ICF	8
#IFL	18

==> Not HD Eligible

All the fields are lists so you can use the button on the right of the fill area to scroll within them.


Note: for IFL only machines (Like EMPEROR), you will find machines where the type ends by **00**. For example, 2964-**700** or 3906-**400** – this means that NO GCP are available for this machine as it is an IFL only machine.

Example of an IFL only machine selection:

2 - Change Configuration	
Machine-Type	3906-700
#zIIP	25
#IFL	25

Here you have chosen a 3906-**700** which contains NO GCP.

With this very configuration, suppose now that you press the Icon for the IFL configuration validation. As you have left 25 zIIPs, you will get an error message:



After pressing OK, the number of zIIP will be set to 0 and the Change Configuration will look like:

2 - Change Configuration	
Machine-Type	3906-700
#zIIP	0
#IFL	25

Of course, you can mix [GCP / zIIP], ICF and IFLs.




9.1.3.1 Notes on LinuxONE machine support :

To make the spreadsheet easy and efficient, LinuxONE machine will be only supported as **IFL only machine** executing z/VM as virtualization software.

When you are done with all these settings **it is mandatory to click the  Icon**. This will check your settings and will bring you to the CONFIG (GCP) worksheet or, if you have an IFL only machine to the CONFIG-IFL worksheet.

9.1.4 Always keep a fresh copy of the initial spreadsheet

It is recommended to always have a fresh copy of the initial spreadsheet – so the  button is useful for that.



9.2 CONFIG SPREADSHEET Usage.

9.2.1 Define the basic LPAR GCP configuration.

There is a cell **#LPARS** | **11** containing the number of currently defined LPARs. We did that because of the IFL and ICF configuration, so we needed to check that the number of LPARs (GCP+IFL+ICF) does not exceed the total number of LPAR supported by the machine.
Just fill the cells in yellow as you would fill the definition at the HMC.

Here is the new layout of the CONFIG spreadsheet before the validation.

ID=IBM Corp. - LPARDesign-HD-V9-T03		Current zPCR Version-9.2a - SpecCfg=YES		LPAR DEFINITION (CP) TOLERATION=%											
CFG-LP-VALID?	NO	#Machine	Shared-Pool												
Machine-type	3906-725	#PhyProc	25	23											
MSU	3 644	#LPs (non-ICF , non-DED)	36	Ded-Pool											
Total Weight	2 415	Ratio LP/PP (base)	1.57	2											
Max LPAR	85	LSPR-AVG-V2R2-MI	31 084												
		#LPARS	11												
LPARNAME	WEIGHT	#LP	SHARE (BY POOL)	RESERVED	Guaranteed #PP	Wkld LSPR	MinReq#LP	Check#LP	HD-HIGH#	HD-MED#	HD-MED%	HD-LOW#	#Active LPs	#Report LPs	
ZWHITE	500	2			Average										
Z015	196	3			Average										
W3906	142	2			Low										
W022	DED	2			Average										
W021	68	2			Average										
W020	300	8			Average										
W017	302	4			Average										
W014	242	3			Low-Avg										
W013	60	1			Average										
S019	300	3			Average										
LPAR8CHR	315	8			Average										

Note: The **Wkld LSPR** column is filled manually or automatically when you import a zPCR study. You can choose (manually) your setting in the following list:



The CPC has already been chosen in the START worksheet. You just must configure the LPARs with their name, Weight (Weight value or DED for dedicated LPs) and number of LPs as you would do in the HMC definition.

9.2.2 Validating the configuration – with **Accept SPECIAL Conf ?** **NO**

This is the regular way of validating the configuration.

Then click on the **Configuration Validation** button (old way) or in the **✓** Icon for GCP.
This will check that the parameters are correctly set.

If errors occur, an error box is displayed; the Check/LP column is filled with the specific error.

The **CFG-LP-VALID?** **NO** is set to NO

You then must correct the errors; rerun the validation until you have **CFG-LP-VALID?** **YES** displayed.
Note: starting with the z13 machine, a cell is displayed. So now, we have 4 possible values: 30, 40, 60 or 85 LPARs.

The cell **Max LPAR** | **85** gives the maximum number of LPAR than can be defined in the machine.



9.2.3 Validating the configuration – with: Accept SPECIAL ConF ?

YES

In this case, you will accept configurations **where** the number of HMC defined LPs is **not consistent** with the number of LPs needed to sustain the share of the LPAR.

The process of validating this kind of configuration has been added and is as follow:


- If the number of defined LPs is less than the number of LPs required to sustain the share of the LPAR, a message will be displayed, BUT, the configuration will be accepted.
- Let's take this example with a focus on the **ZWHITE** LPAR:

ID=IBM Corp. - LPARDdesign-HD-V9-T03 Current zPCR Version-9.2a - SpecCfg=YES LPAR DEFINITION (CP)										
CFG-LP-VALID?	YES			#Machine	Shared-Pool					Configuration Validation
		#PhyProc	25			#LPs (non-ICF, non-DED)	36	Ded-Pool		
Machine-type	3906-725					Ratio LP/PP (base)	1.57			
MSU	3 644					LSPR-AVG-V2R2-MI	31 084			
Total Weight	2 415					#LPs	11			
Max LPAR	85									
LPARNAME	WEIGHT	#LP	%SHARE (By Pool)	RESERVED	Guaranteed#PP	Wkld LSPR	MinReq#LP	Check#LP	HD-supported on 3906	
ZWHITE	500	2	20.7%		2.00	Average	5	OK(a)	HD-HIGH#	
Z015	196	3	8.1%		1.87	Average	2	OK	HD-MED#	
W3906	142	2	5.9%		1.35	Low	2	OK	HD-MED%	
W022	DED	2	100.0%		2.00	Average	2	OK	HD-LOW#	
W021	58	2	2.4%		0.55	Average	1	OK	#Active LPs	
W020	300	8	12.4%		2.86	Average	3	#NL>2	#Report LPs	
W017	302	4	12.5%		2.88	Average	3	OK		
W014	242	3	10.0%		2.30	Low-Avg	3	OK		
W013	60	1	2.5%		0.57	Average	1	OK		
S019	300	3	12.4%		2.86	Average	3	OK		
LPAR8CHR	315	8	13.0%		3.00	Average	3	#NL>2		

We see that ZWHITE LPAR has a Weight of 500 which gives a %Share of 20.7% of the Shared Pool and thus needs a Minimum Required #LP of 5.

But only 2 LP are defined, and this is done on purpose.

During the process, the following pop-up message will be displayed:



The LPAR definition will be accepted and the Guaranteed#PP (a key value for HiperDispatch® computing) will be replaced by the number of LPs set in the #LP column.

To reflect this “acceptation” the Guaranteed#PP column is set to bold and blue and the Check#LP column will receive the value **OK(a)**.

After the validation, the regular HiperDispatch® process can carry on but it will use the “replaced” value in Guaranteed#PP.



9.2.4 Sorting selected columns.

The capability of sorting selected columns is there:



These columns have the buttons  in their header. Sort can be Ascending or Descending depending on the button you push.

Only columns that have these buttons can be sorted. The following picture shows what columns you can sort on the CONFIG sheet.

ID=IBM Corp. - LPARDesign-HD-V9-T03		Current zPCR Version-9.2a - SpecCfg=YES		LPAR DEFINITION (CP)	
CFG-LP-VALID?	YES	#PsiProc	#Shared-Pool		
Machine-type	3906-725	#LPs (non-ICF, non-DED)	25 36	Configuration Validation	
MSU	3 644	Ratio LP/P (base)	1.57	Delete selected LPAR	
Total Weight	2 415	LSPR-AVG-VZR2-MI	31 084		
Max LPAR	85	#LPs	11		
LPAR NAME		WEIGHT	#LP	%SHARE (By Pool)	
RESERVED		Guaranteed #PP	Wkld LSPR	MinReq#LP	Check#LP
HD-supported on 3906		HD-HIGH#	HD-MED#	HD-MED%	HD-LOW#
#Active LPARs		#Report LPAR			

Note: sorting on the CONFIG sheet will sort (on the same column name) the related column on the other two sheets:

CONFIG-zXXP – because the LPARNAME is derived from the CONFIG sheet

CONFIG-MSU – because the LPARNAME, #LP and Weight are derived from the CONFIG sheet



9.2.5 Explanation of some columns.

**%SHARE
(By Pool)**

- gives the %SHARE of the LPAR (by pool of LP, Shared / DEDicated)

**Guaranteed
#PP**

- This is: "%SHARE x #of Physical processors (shared pool)" – a fundamental metric for the HiperDispatch calculation.

Note: with **Accept SPECIAL ConF ? YES** this value is not calculated but replaced by the number of defined LPs.

MinReq#LP


- This gives the minimum number of LP needed to sustain the %SHARE.

Note: with **Accept SPECIAL ConF ? YES** and if there are less defined LPs than required, this column will

Check#LP
OK(a)

have the value:

Note that now all the messages are in a single Box:



All the message boxes display the current supported zPCR Version.

The **RESERVED** column is currently used to display information messages like "rules" for a specific machine (for the GCP processing at that time).



9.2.6 Computing the HiperDispatch® number of LPs.

Just push the appropriate button or Icon and the following columns will be filled with the calculated values.

HD-HIGH#	HD-MED#	HD-MED%	HD-LOW#	#Active LPs	#Report LPs
----------	---------	---------	---------	-------------	-------------

HD-HIGH#: #of HighShare LPs or **VH**

HD-MED#: #of MediumShare LPs or **VM**


HD-MED%: Entitlement of the MediumShare LPs

HD-LOW#: #of LowShare LPs or **VL**.

#Active LPs: This is the number of real life active LPs considering that WLM will always “UnPark” a LowShare LP in a 2 LP configuration with a MediumShare LP and a LowShare LP. This number can be compared to the number of LP you initially set for the LPAR to evaluate the HiperDispatch® effect.

#Report LP: The sum of VH and VM according to the basic HiperDispatch® LP spread calculation. This number is the one reported by RMF but remember that on a 2 LP configuration the second LP is always UnParked.

When the calculation is completed you will receive this pop-up box:



Otherwise, error messages will be sent.

The colors of the LP entitlement have been set to highlight HighShare LPs or MediumShare LPs that have an entitlement of 100% as shown in the below picture:

CFG-LP-VALID?	YES	HD supported on 8561								
Machine-type	8561-718	LPARNAME	WEIGHT	#LP	HD-HIGH#	HD-MED#	HD-MED%	HD-LOW#	#Active LPs	#Report LPs
MSU	3 213	W013	142	2	0	2	71.0%	0	2	2
Total Weight	1 600	W014	242	3	1	2	71.0%	0	3	3
Max LPAR	85	W015	196	3	1	1	96.0%	1	2	2
		W017	302	4	2	2	51.0%	0	4	4
		W018	60	2	0	1	60.0%	1	2	1
		W019	300	3	3	0	N/A	0	3	3
		W020	300	5	2	1	100.0%	2	3	3
		W021	58	2	0	1	58.0%	1	2	1
		W022	DED	2	2	0	N/A	0	2	2

LPAR W020 has 2 VH LPs, 1 VM@100% and 2 VL - so you can see the way the cells are colored.
In this case, a VM is needed to be the anchor point of future UnParked VLs




A warning message will be displayed in the Check#LP column if the number of VL is > 2 as shown in this example:

LPARNAME	WEIGHT	#LP	%SHARE (By Pool)	RESERVED	Guaranteed #PP	Wkld LSPR	MinReq#LP	Check#LP
W3906	142	2	5.9%		1.35	Low	2	OK
W014	242	3	10.0%		2.30	Low-Avg	3	OK
Z015	196	3	8.1%		1.87	Average	2	OK
W017	302	4	12.5%		2.88	Avg-High	3	OK
ZWHITE	500	2	20.7%		2.00	High	5	OK(a)
S019	300	3	12.4%		2.86	Average	3	OK
W020	300	8	12.4%		2.86	Average	3	#VL>2
W021	58	2	2.4%	New 3906 Rule	0.55	Average	1	OK
W022	DED	2	100.0%		2.00	Average	2	OK
W013	60	1	2.5%		0.57	Average	1	OK
LPAR8CHR	315	8	13.0%		3.00	Average	3	#VL>2

LPARs W020 and LPAR8CHR have this warning.

9.2.7 Linking to zPCR.



When the button  is pressed, this will create a *.zpcr* study file from the LPARDesign spreadsheet or will update the current LPARDesign spreadsheet with an existing *.zpcr* study file. See the chapter **LINK with zPCR** for more information.

zPCR Menu

Or you can use the  button in the Task Bar to call the zPCR link.



9.2.8 Deleting LPARs.

A button **Delete selected LPAR** is provided to properly delete selected LPAR. This was a long term requirement as it is not allowed to delete an LPAR with just deleting the EXCEL row containing this LPAR: after manual deletion, the number of row was less than expected and this was producing errors in the spreadsheet.


To delete LPAR(s):

- Select the LPAR(s) you want to delete
- If you want to delete more than one LPAR , select the first one, **keep the CTRL key pressed**, then select the other LPARs.

In this scenario, LPARs W014 and W018 are selected:

LPARNAME	WEIGHT	#LP
W013	142	2
W014	242	3
W015	196	3
W017	302	4
W018	60	2
W019	300	3
W020	300	5
W021	58	2
W022	DED	2

Then press the **Delete selected LPAR** button and you will get the following message box:



Note that the deletion has been done in the CONFIG-zXXP and the CONFIG-MSU too.

Never delete a row in any Worksheet!



9.3 CONFIG-MSU SPREADSHEET Usage.

9.3.1 General usage notice:

As usual the LPAR's Name, #LCP and Weight are taken from the CONFIG spreadsheet, so only the yellow columns named:

Defined Capacity Limit
Capacity Group Name
Capacity Group Limit [MSU]

have to be filled to use this part of the tool.

Definitions					
Lpars	LCPs	Weight	Defined Capacity Limit	Capacity Group Name	Capacity Group Limit [MSU]

One possibility on modern z Systems with z/OS is to control the MSU consumption with the help of group capping. Group capping provides the fact that partitions can consume more MSU during a capping phase when other partitions of the same capacity group do not require their capacity share. On the other hand it is often difficult to understand how the partitions are being capped especially when group capping and individual defined capacity limits are combined. The Config-MSU tab provides some assistance in identifying the capping mechanism for the partitions under the assumption that all partitions request their capacity share during the capping phase. Figure 1 shows an example for an environment with 6 partitions from which 5 belong to a capacity group GRP1, and two of these partitions have individual defined capacity limits.

Definitions					CEC/LCP based					Group Calculations							Result		
Lpars	LCPs	Weight	Defined Capacity Limit	Capacity Group Name	Capacity Group Limit [MSU]	Share [%]	MSU at Weight	Theoretical Usable MSU	Total Group Weight	Group Share [%]	Group Share [MSU]	Possibly Donated MSU	Total Donated MSU	Possible Group Receiver	Group Receiver Share [%]	Received Donated MSU	Maximum Consumable MSU	Comment	
SYS1	10	500	GRP1	1,000	40.0%	476.4	1,151.0	1,050	47.5%	476.2		81.0	YES	76.9%	62.3	538.5	cap pattern or negative phantom weight		
SYS2	5	250	200	GRP1	1,000	20.0%	238.2	595.5	1,050	23.8%	238.1	38.1				200.0	positive phantom weight		
SYS3	2	150	100	GRP1	1,000	12.0%	142.9	238.2	1,050	14.3%	142.9	42.9				100.0	positive phantom weight		
SYS4	2	100		GRP1	1,000	8.0%	95.3	238.2	1,050	9.5%	95.2					107.7	cap pattern or negative phantom weight		
SYS5	1	50		GRP1	1,000	4.0%	47.6	119.1	1,050	4.8%	47.6					53.8	cap pattern or negative phantom weight		
SYS6	4	200	100			16.0%	190.6	476.4								100.0	positive phantom weight		

Figure 1 CONFIG-MSU Example

9.3.2 LPAR and Capacity Definitions

Definitions						Share [%]
Lpars	LCPs	Weight	Defined Capacity Limit	Capacity Group Name	Capacity Group Limit [MSU]	
SYS1	10	500		GRP1	1,000	40.0%
SYS2	5	250	200	GRP1	1,000	20.0%
SYS3	2	150	100	GRP1	1,000	12.0%
SYS4	2	100		GRP1	1,000	8.0%
SYS5	1	50		GRP1	1,000	4.0%
SYS6	4	200	100			16.0%

The definitions part shows the defined LPARs, the number of logical processors (LCPs) per partition, and the weight of each partition. The weight determines the “Share [%]” each partition has from the CEC. The Capacity definitions encompass a possible Defined Capacity Limit for each partition, the Group name if the partition belongs to a capacity group and the Capacity Limit of the Group.



Figure 2 CONFIG-MSU Definitions

CEC/LCP based		
Share [%]	MSU at Weight	Theoretical Usable MSU
40.0%	476.4	1,191.0
20.0%	238.2	595.5
12.0%	142.9	238.2
8.0%	95.3	238.2
4.0%	47.6	119.1
16.0%	190.6	476.4

The next part of the spreadsheet converts the weight definition into an MSU value. MSU at Weight tells how much MSU are guaranteed to the partition by its weight definition. The theoretical usable MSU value describes how many MSU can be consumed when all LCPs of the partition are used to 100%.

Figure 2 Usable MSU for each partition

9.3.3 Group Calculation

Group Calculations							
Total Group Weight	Group Share [%]	Group Share [MSU]	Possibly Donated MSU	Total Donated MSU	Possible Group Receiver	Group Receiver Share [%]	Received Donated MSU
1,050	47.6%	476.2		81.0	YES	76.9%	62.3
1,050	23.8%	238.1	38.1				
1,050	14.3%	142.9	42.9				
1,050	9.5%	95.2		81.0	YES	15.4%	12.5
1,050	4.8%	47.6		81.0	YES	7.7%	6.2

Figure 3 Group Calculations

Figure 4 depicts group related metrics. For distributing the MSU within a group it is necessary to understand the total weight of all partitions within the group as well as the share of each partition within the group. The group share is expressed as a percentage value and a MSU value.

If a partition has a defined capacity limit which is smaller than its Group share, the partition is not able to consume all of the MSU which it is entitled to by the group definition. The MSU which it is not able to use can potentially be donated to other partitions when group capping and individual capping is in effect for the partition. The “Total Donated MSU” can now be distributed between the receiver partitions. Each receiver has a share based on its weight and receives the corresponding portion of the total donated MSU.

Result	
Maximum Consumable MSU	Comment
538.5	cap pattern or negative phantom weight
200.0	positive phantom weight
100.0	positive phantom weight
107.7	cap pattern or negative phantom weight
53.8	cap pattern or negative phantom weight
100.0	positive phantom weight

The result section now tells how much MSU each partition can consume under the assumptions that all partitions use their share and that all capping limits are being reached. The Comment column then displays which capping technology is being used.

Figure 4 Group Capping Results

Notice: Starting with zEC12 GA2 and z/OS 2.1 the **cap pattern technology has been replaced by a negative phantom weight technology**, therefore which technology is being used depends on the hardware and software level.



9.3.4 Other buttons functions:

Clear Definitions


This will clear de MSU definitions (Yellow columns)

Clear Calculations

This will clear the calculation part after a partial modification of the definitions

Calculate

When the definitions are ok, press this button to calculate them. The following information box will appear:



9.3.5 Explanation of this tab header:

The LPAR configuration is taken from the CONFIG tab.

DEDicated processors may exist in the definition – if it is the case this particularity is shown in the Shared Pool cell when the number of physical processor in the Shared Pool is different from the number of physical processors of the actual physical machine.

This is shown in the following example:

CEC	2964-712	PCPs	12	MSU	1 891	Total Weight	1 000	Shared Pool	10
-----	----------	------	----	-----	-------	--------------	-------	-------------	----

The definitions of this example are:

Definitions						
Lpars	LCPs	Weight	Defined Capacity Limit	Capacity Group Name	Capacity Group Limit [MSU]	
W013	3	300		GRP1	1 000	
W014	3	200	200	GRP1	1 000	
W015	2	200	100	GRP1	1 000	
W017	2	140		GRP1	1 000	
W018	2	10		GRP1	1 000	
W019	2	DED				
W020	2	100	100			
W021	2	50	100			

The physical machine has 12 PCP

But we have an LPAR (W019) with 2 DEDicated PCP

So the Shared Pool is 10 PCP

Note#1: The Weight cell format of the DEDicated LPAR is in red.

Note#2: sorting on the CONFIG sheet will sort (on the same column name) the related column on two other worksheets:

CONFIG-zXXP – because the LPARNAME is derived from the CONFIG sheet

CONFIG-MSU – because the LPARNAME, #LP and Weight are derived from the CONFIG sheet



9.4 CONFIG-ZXXP SPREADSHEET Usage.

9.4.1 Only zIIP are supported in this release.

Once you are done with the CP configuration you can use the set of Icons to be directed to the zIIP configuration spreadsheet if needed.

The LPAR NAMES are automatically filled.

Never delete an LPAR in this sheet – do it from the CONFIG sheet and use the “Delete selected LPAR” button

Remember: The number of ziIP has been filled in the START spreadsheet and can be seen in

If you want to change it, go back to the START spreadsheet.

Note that the rule concerning the total number of zIIP is enforced and checked (2 zIIP / 1 GCP).

It is not the standard rule which is based on the number of purchased CP, but we cannot know what this number is.

Then fill the Weight (Weight value or DED for dedicated zIIP) and number of LPs for each LPAR.

Clear the cells (Weight and number of LP) for the LPARs that are not concerned by the zIIP configuration.

NEVER clear the LPAR name.

Then, click on the **Configuration Validation** button (old way) or the  Icon for zIIP. This will check the configuration and calculate the HiperDispatch® number of LPs.

If errors occur, an error box is displayed and character "E" is set on the Error column of the current LPAR:
Example of error – the machine has **25** physical zIIP, but one has defined **26** LP in the W020 LPAR:



The column named **#Act-LPs** has the same meaning that the one in the CONFIG spreadsheet.

The zXXP configuration is checked in two phases:

- One for the Configuration Validation (e.g.: LP numeric and so on). Its name is “Initial Configuration”.
- One for the HiperDispatch® Configuration calculation. Its name is “Final Configuration”.

A new **Information** column has been added to provide specific information for a specific machine rule.

Note#2: sorting on the CONFIG sheet will sort (on the same column name) the related column on two other worksheets:

CONFIG-zXXP – because the LPARNAME is derived from the CONFIG sheet

CONFIG-MSU – because the LPARNAME, #LP and Weight are derived from the CONFIG sheet




9.4.2 Support for Special Configuration for zIIPs:

This is the same rule than for GCP configuration.

If you want to set a number of zIIP LPs that is below the number of required zIIP LPs, you can do it by selecting **Accept SPECIAL ConF ? YES** in the START spreadsheet (this information will be the same for both GCP and zIIP).

When you are in the situation where the number of zIIP LPs is below the number of required LPs and you have selected this option, you will have this message box(read the information for the ZWHITE LPAR) :



And the target LPAR will have its number of guaranteed LP in bold/blue as shown below for the ZWHITE LPAR :

zIIP			%SHARE by pool	Guaranteed# PP	HD supported on 3906						
LPARNAME	WEIGHT	#LP			HD-HIGH#	HD-MED#	HD-MED%	HD-LOW#	#Act-LPs	Error	Information
W3906	142	2	6%	1.35	0	2	67.6%	0	2		
W014	242	3	10%	2.30	1	2	65.2%	0	3		
Z015	196	3	8%	1.87	1	1	88.7%	1	2		
W017	302	4	13%	2.88	2	1	87.6%	1	3		
ZWHITE	500	2	21%	2.00	2	0	N/A	0	2	OK(a)	
S019	300	3	12%	2.86	2	1	85.7%	0	3		
W020	300	8	12%	2.86	2	1	85.7%	5	3	#VL>2	
W021	58	2	2%	0.55	0	2	27.6%	0	2		New 3906 Rule
W022	DED	2	100%	2.00	2	0	N/A	0	2		
W013	60	1	2%	0.57	0	1	57.1%	0	1		
LPAR8CHR	315	8	13%	3.00	2	1	100.0%	5	3	#VL>2	

In the error column, the characters **OK(a)** will be displayed too.

The recommendation on the number of VL is displayed too (as for W020 and LPAR8CHR LPARs).



9.5 THE CONFIG-IFL SPREADSHEET USAGE.

As for GCPs, just fill the cells in yellow.

Remember that the number of IFLs has been set in the START spreadsheet. This is the only place to change it. Here is the layout of the spreadsheet:


ID=IBM Corp. - LPARDdesign-HD-V9-T03 Current zPCR Version-9.2a - SpecCfg=YES LPAR DEFINITION (IFL)											
CFG-LP-VALID?	NO										
Machine-type	3906-725										
IFL#Procs	25										
Max LPAR	85										
IFL-Shared-Pool	23										
IFL-DED-Pool	2										
IFL-Weight	2415										
IFL-Valid?	NO										
IFL-#LPARS	11										
Configuration Validation Delete selected LPAR											
Go back to START to modify the IFL#Procs											
IFL											
LPARNAME	WEIGHT	#LP	%SHARE (By Pool)	Guaranteed #PP	HD-HIGH#	HD-MED#	HD-MED%	HD-LOW#	#Act-LPs	Error	Information
↑ ↓	↑ ↓	↑ ↓	↑ ↓	↑ ↓	↑ ↓	↑ ↓	↑ ↓	↑ ↓	↑ ↓		
ZVM11	315	8									
ZVM4	302	4									
ZVM6	300	3									
ZVM7	300	8									
ZVM2	242	3									
ZVM5	500	2									
ZVM9	DED	2									
ZVM3	196	3									
ZVM1	142	2									
ZVM10	60	1									
ZVM8	68	2									

You must specify the **LPAR Name** as it cannot be copied from somewhere else (as for zIIP).

The configuration validation is done in two steps as for zIIP (INITIAL and FINAL).

As for GCPs you can properly delete an LPAR.

If you have GCPs too, **you must validate the GCP configuration before validating the IFL configuration** otherwise you will get this error message:



Note: depending on the way you have entered the number of IFL, you will be automatically directed to this IFL configuration spreadsheet – this is the case for an IFL only configuration.



Here is the spreadsheet after having click on the [Configuration Validation](#) button (old way) or in the Icon.



ID=IBM Corp. - LPARDesign-HD-V9-T03			Current zPCR Version-9.2a - SpecCfg=YES			LPAR DEFINITION (IFL)						
CFG-LP-VALID?	YES		IFL-Shared-Pool	23		Configuration Validation		Delete selected LPAR				
Machine-type	3906-725		IFL-DED-Pool	2								
IFL#Procs	25		IFL-Weight	2415								
Max LPAR	85		IFL-Valid?	YES								
			IFL-#LPArS	11								
IFL						HD supported on 3906						
LParName	Weight	#LP	%SHARE (By Pool)	Guaranteed #PP		HD-HIGH#	HD-MED#	HD-MED%	HD-LOW#	#Act-LPs	Error	Information
ZVM11	315	8	13.0%	3.00		2	1	100.0%	5	3	#VL>2	
ZVM4	302	4	12.5%	2.88		2	1	88.0%	1	3		
ZVM6	300	3	12.4%	2.86		2	1	86.0%	0	3		
ZVM7	300	8	12.4%	2.86		2	1	86.0%	5	3	#VL>2	
ZVM2	242	3	10.0%	2.30		1	2	65.0%	0	3		
ZVM5	500	2	20.7%	2.00		2	0	N/A	0	2	OK(a)	
ZVM9	DED	2	100.0%	2.00		2	0	N/A	0	2		
ZVM3	196	3	8.1%	1.87		1	1	87.0%	1	2		
ZVM1	142	2	5.9%	1.35		0	2	67.5%	0	2		
ZVM10	60	1	2.5%	0.57		0	1	57.0%	0	1		
ZVM8	58	2	2.4%	0.55		0	1	55.0%	1	2		

All the rules and error messages are the same as for GCP.

9.5.1 Sorting selected columns.

We have introduced the capability of sorting selected columns.

These columns have the buttons  in their headers. Sort can be ascending or descending depending on the button you push.

Only columns that have these buttons can be sorted. The following picture shows what columns you can sort on the CONFIG-IFL sheet.



9.6 THE CONFIG-ICF SPREADSHEET USAGE.

For the link with zPCR to be complete, the transfer of the ICF configuration that might be include in a zPCR study is available.

ICFs are not HiperDispatch® eligible, so a simple calculation is done in this spreadsheet.

ID=IBM Corp - LPARDdesign V11-T01 Current zPCR Version-9.4 - SpecCfg=YES LPAR DEFINITION (ICF)											
CFG-LP-VALID?	YES	ICF-Shared-Pool		4	Configuration Validation			Delete selected LPAR			
Machine-type	8561-718	ICF-DED-Pool		14							
ICF#Procs	18	ICF-Weight		400							
Max LPAR	85	ICF-Valid?		YES							
		ICF-#LPARs		9							
ICF (%Share Only Calculation)											
LPARNAME	WEIGHT	#LP	%SHARE (By Pool)	Guaranteed #PP	DED#	SHR#	SHR% by LP	Reserved	#Act-LPs	Error	Information
ICF1	200	2	50.0%	2.000	0	2	100.0%		2		
ICF2	150	2	37.5%	1.500	0	2	75.0%		2		
ICF3	50	2	12.5%	0.500	0	2	25.0%		2		
ICF4	DED	3	21.4%	3.000	3	0	N/A		3		
ICF5	DED	2	14.3%	2.000	2	0	N/A		2		
ICF6	DED	2	14.3%	2.000	2	0	N/A		2		
ICF7	DED	2	14.3%	2.000	2	0	N/A		2		
ICF8	DED	2	14.3%	2.000	2	0	N/A		2		
ICF9	DED	3	21.4%	3.000	3	0	N/A		3		

Here we have a %Share by pool (DED or Shared

The Guaranteed #PP is available to check if the correct number of LP has been set to sustain the Share.

Of course, all the usual error messages are available and the calculations are compliant with the “Accept Special Config” rules.

SHR% by LP

Note the column: it shows what is the %Share for each LP of the LPAR.

In the previous example, we can see that LPAR ICF1 has a Guaranteed #PP of 2 and we have set 2 LPs, So each LP will have a %Share of 100% - In this case we set a color in the cell.

LPAR ICF2 has a Guaranteed #PP of 1.5 and we have set 2 LPs. So each LP will have $(1.5/2)*100$ giving 75% of %Share.

This is a usual calculation in horizontal mode.

9.6.1 Sorting selected columns



You can sort the data using the buttons (ascending and descending)



9.7 SYNTHESIS SPREADSHEET Usage.

The result of the HiperDispatch® activation can be viewed in the SYNTHESIS spreadsheet as shown below.

ID=IBM Corp. - LPARDdesign-HD-V9-T01		Current zPCR Version-9.0e - SpecCfg=YES SYNTHESIS	
HiperDispatch Effect - GCP		HiperDispatch Effect - IFL	
#LP (Shared Pool Only)	W/O HD	W/ HD	W/O HD
#LP (Shared Pool Only)	36	24	36
LP/PP ratio (Shared Pool Only)	1.57	1.04	1.57
Global Statistics			
LPAR Statistics			
#LPAR-TOTAL	11		11
#LPAR w/HighShare LP (Total)	8		8
#LPAR w/DED LP	1		1
LP Statistics			
#HighShare LP (Total)	14		14
#HighShare LP (DED)	2		2
#MediumShare LP	12		12
#LowShare LP	12		12
HiperDispatch Effect - zIIP			
#LP (Shared Pool Only)	W/O HD	W/ HD	W/O HD
#LP (Shared Pool Only)	38	26	38
LP/PP ratio (Shared Pool Only)	1.65	1.13	1.65
Global Statistics			
LPAR Statistics			
#LPAR with zIIP	11		11
#LPAR w/HighShare LP (Total)	8		8
#LPAR w/DED LP	1		1
LP Statistics			
#HighShare LP (Total)	14		14
#HighShare LP (DED)	2		2
#MediumShare LP	12		12
#LowShare LP	26		26

With these numbers, you can figure out how many VH, VM and VL you have.
 You can see the HiperDispatch® effect on the number of actual active LPs.



9.8 EXPERT SPREADSHEET Usage.

EXPERT is available for CGP, zIIP and IFL. The layout is as follow:



You can have a direct access to a particular EXPERT Note in using the icon on the navigation BAR.

When the note advises you to increase a Weight, you will now have the amount of this increase. Obviously, the calculation can only be done at constant Total Weight – so if you increase the Weight to xx for an LPAR, you must decrease the Weight from xx for another LPAR.

Here is an example of what is provided in this specific case:

LPAR	Suggested Improvement Notes - GCP - Machine Type = 3906
W3906	(R1-GCP) - Due to the 0.5 rule, a small increase of the Weight could lead to have a Full VH Your current Guaranteed#PP is 1,35 - raising it to 1.5 would give you 1-VH and 1-VM@50%! The New Weight should be : 158 - The current Weight is : 142 - So you must decrease another Lpar Weight by : 16 to keep Total Weight(2415) constant

9.8.1 EXPERT Notes for GCP.

When you push the button (old way), or the icon, you may (or not) have advices on how to optimize your current configuration.

Here are the current rules used to provide these advices:

9.8.1.1 The rules used for advices in GCP:

Rule#1:

If you have 1 VH and the decimal part is between 0.35 and less than 0.5, you can have 1VH and 1 VM@50% if you raise your Weight to have the decimal part to at least 0.5. Otherwise, you will have two VM.

- On z13, this rule is no longer valid: a new way of calculating the spread of LPs has been provided for an LPAR which has 1VH and 1VM@x%.
- On z13, whatever the x% is, you will get 2VH@[$(1+x)/2$]%.

On z14, the 1.5 rule is back.

Rule#2:

Same than Rule#1, with more than 1 VH.

Otherwise, one VH will be moved to the VM pool.

Rule#3:

If the decimal part is higher than 0.80 (meaning that you are not far from having a new VH), a small increase in the Weight could lead to have a new VH.

Rule#4:

It is the opposite on Rule#3.

If the decimal part is lower than 0.05 (meaning that you potentially burn an existing VH), decreasing the Weight could lead to have a VH.

Rule#5:

This is just a warning to remember you that if you have defined 2 LPs and you do not have a VH, the second LP (which is a VL) will always be Unparked.

This rule applies to all machines but the z14.



Rule#6:

This is just a warning to remember you that if you have an integer number of VH and you have defined more LPs than VHs (so having VL), one VH will be in fact a VM@100%.

Rule#7:

This is to alert that you have specified less LPs than needed but you have set ACCEPT SPECIAL CONFIG to YES.

This will influence the HiperDispatch® calculation of VH, VM and VL for the other LPARs.

This is the case for what we call WHITE SPACE LPARs.

Rule#8:

The number of LP must be set properly for not having so much VL. A best Practice document is available as a TechDoc TD106388. This Rule warns you if you are above the recommendation of this Best practice.


Here is a partial example of what is produced:

LPAR	Suggested Improvement Notes - GCP - Machine Type = 3906
W3906	(R1-GCP) - Due to the 0.5 rule, a small increase of the Weight could lead to have a Full VH Your current Guaranteed#PP is 1,35 - raising it to 1.5 would give you 1-VH and 1-VM@50% The New Weight should be : 158 - The current Weight is : 142 - So you must decrease another Lpar Weight by : 16 to keep Total Weight(2415) constant
W014	No special Comment or Advice for this LPAR
Z015	(R3-GCP) - You have 1-VM with an entitlement of 87% Your current Guaranteed#PP is 1,87 - raising the Weight and removing 1-LP would give you 2-VH but with less flexibility" The New Weight should be : 210 - The current Weight is : 196 - So you must decrease another Lpar Weight by : 14 to keep Total Weight(2415) constant [+] NOTE - You have 1VM and 1VL When ALL Vls will be UnParked, each VM and VL will have an entitlement of 43,33%
W017	(R3-GCP) - You have 1-VM with an entitlement of 88% Your current Guaranteed#PP is 2,88 - raising the Weight and removing 1-LP would give you 3-VH but with less flexibility" The New Weight should be : 315 - The current Weight is : 302 - So you must decrease another Lpar Weight by : 13 to keep Total Weight(2415) constant [+] NOTE - You have 1VM and 1VL When ALL Vls will be UnParked, each VM and VL will have an entitlement of 43,81%
ZWHITE	(R7-GCP) - The number of specified LP is not sufficient but accepted However, this LPAR will influence the total WEIGHT and thus the HiperDispatch spread in VH, VM and VL for the others LPARs

The Rule number of the advices is shown in the ligne.

If no advice is found you will have the text “[No special Comment or Advice for this LPAR](#)”.

A final pop-up window will show you how many LPARs have advices:



Note : This facility is only available if you have a valid configuration.



9.9 EXPERT Notes for zIIPs.

EXPERT notes are provided for the zIIPs configuration in clicking on the  button (old way) or clicking on the  Icon on the navigation BAR

[Click for EXPERT NOTES - zIIP](#)

Mots of the rules are quite the same as for the GCPs.

Here are some specific rules for zIIP:

Rule#9-zIIP:

Informs that the %Share of the zIIP for this LPAR is low (as shown for LPAR W020).

The message is currently triggered if the %Share is less than 5%.

Rule#10-zIIP:

The number of LP must be set properly. A best Practice document is available as a TechDoc TD106388. This Rule warns you if you are above the recommendation of this Best practice.

Here is a partial example of what is provided:

LPAR	Suggested Improvement Notes - zIIP - Machine Type = 3906
W020	(R3-zIIP) - You have 1-VM with an entitlement of 85,7%" Your current Guaranteed#PP is 2,86 - raising the Weight and removing 5-LP would give you 3-VH but with less flexibility" The New Weight should be : 315 - The current Weight is : 300 - So you must decrease another Lpar Weight by : 15 to keep Total Weight(2415) constant (R10-zIIP) - *WARNING* - The number of VL (5) is above the IBM Best Practice See: http://www-03.ibm.com/support/techdocs/atsmastr.nsf/WebIndex/TD106388 - for this Best Practice [+] NOTE - You have 1VM and 5VL When ALL Vls will be UnParked, each VM and VL will have an entitlement of 14,29%
W021	(R9-zIIP) - the %SHARE is very low 2,4% This might lead to an ineffective use of the zIIP
W022	No special Comment or Advice for this LPAR
W013	(R9-zIIP) - the %SHARE is very low 2,5% This might lead to an ineffective use of the zIIP

9.10 EXPERT Notes for IFL.

EXPERT notes are provided for IFL when you press the  button (old way) or clicking on the  Icon on the navigation BAR.

[Click for EXPERT NOTES - IFL](#)

The rules **are the same as** for GCPs.



9.11 DASHBOARD SPREADSHEET Usage.

This graphic is generated when you push the button related (if appropriate) to the PU type you select. We have 4 types : GCP, zIIP, IFLs and ICFs as shown below.

You can go directly to the appropriate DASHBOARD using the  Icon on the navigation BAR.

ID=IBM Corp - LPARDdesign V11-T01 Current zPCR Version-9.4 - SpecCfg=YES DASHBOARD For GCP Processors																										
GCP	zIIP	Legend :		LP High	x%	LP Medium or SHR with x% of Share	LP Low	x%	LP Low Always Unparked with a Share of x%	LP DED																
IFL	ICF	LP01	LP02	LP03	LP04	LP05	LP06	LP07	LP08	LP09	LP10	LP11	LP12	LP13	LP14	LP15	LP16	LP17	LP18	LP19	LP20	LP21	LP22	LP23	LP24	LP25

The first lines show a legend explaining the colors of the different LPs assignments.

The following lines (by LPARs) gives the layout of each LPAR:

LPAR Name	% Share	Guarant #PP	LP01	LP02	LP03	LP04	LP05	LP06	LP07	LP08	LP09	LP10
W013	8.9%	1.42	71.0%	71.0%								
W014	15.1%	2.42		71.0%	71.0%							
W015	12.3%	1.96			96.0%							
W017	18.9%	3.02				51.0%	51.0%					
W018	3.8%	0.60	30.0%		30.0%							
W019	18.8%	3.00										
W020	18.8%	3.00				100%						
W021	3.6%	0.58	29.0%		29.0%							
W022	DED	2.00										

For example, we can see that:

LPAR W013 has 2 VM@71%

LPAR W014 has 1 VH and 2VM@71%

LPAR W015 has 1VM@96% and 1VL


LPAR W018 has 1VM30% and a VL@30% always unparked

LPAR W020 has 2VH, 1VM@100% and 2VL.

LPAR W022 has 2 DED LPs – The color is in dark grey.



The graphic is not limited to 25 LPs (LP0 to LP25) as shown in the above first picture, if you have more than 25 defined LPARs you will get this layout:



The W013 LPAR was defined with 26 LPs – so a second line is started for the 1 remaining LP (and so on).

9.11.1 DASHBOARD for zIIP enhancement.

When an LPAR does not have a zIIP allocation, this LPAR will be in dark grey color in the DASHBOARD

LPAR Name	% Share	Guarant #PP	LP01	LP02	LP03	LP04	LP05	LP06
W013	8.9%	1.60		59.8%				
W014	15.1%	2.72				72.2%		
W015	12.3%	2.21			60.3%	60.3%		
W017	18.9%	3.40				69.9%	69.9%	
W018	3.8%	0.68	33.8%	33.8%				
W019	18.8%	3.00						
W020	18.8%	3.38				68.8%	68.8%	
W021	3.6%	0.65	32.6%	32.6%				
W022	0.0%	0.00						

LPAR W022 does not have a zIIP allocation



10. LINK with zPCR.

10.1 General considerations on this feature.

This feature helps creating a zPCR Basic study file from LPARDesign or to upload in LPARDesign an existing zPCR Basic study file.




To use this function click on the  button located in the CONFIG worksheet.

Or use the  Icon on the navigation BAR.

To generate a reliable zPCR Basic study file, you need to have your GCP, IFL and zIIP configurations validated. As you know, every time the spreadsheet is loaded, the cells containing the configurations validations status are set to NO, so, **all the configurations validations MUST BE DONE**.

If you do not perform this process, you will have the following error messages:

Example for GCP:



10.2 Current limitations of the link to zPCR feature.

10.2.1 Specifying an LPAR with unsufficient number of LPs to sustain the share

This could lead to have a problem when this LPARDesign study is exported to zPCR.
zPCR requires that you set at least one LP, but you will face the problem that you do not have sufficient LPs to sustain the share.

In this case you will have this zPCR message:

Note: A partition's weight indicates more capacity than its LCPs can provide; Unusable capacity is redistributed to other partitions within the CP pool

10.2.2 Processors type.

HiperDispatch® is available on the z/OS operating system on GCP, zIIP and IFL processors types.
To make the study with zPCR easier, we have added the support of the ICF, even if ICF are not HiperDispatch® eligible.

10.2.3 Reference CPU.

   **2094-701 @ 593,00 MIPS** as a reference CPU.
Again, you might be led to change this default.

10.2.4 zPCR Version.



The LPARDdesign code is usually in sync with the last zPCR version. The current supported version is displayed in the message boxes. zPCR usually allows that a study with the n-1 version to be uploaded.


10.2.5 z/OS Version.

In this current release of LPARDdesign we have set the z/OS Version to the LSPR Version so z/OS V2R3.

10.3 Using the zPCR EXPORT feature.

This feature export the current LPARDdesign definition to a zPCR Basic study file.

After all configurations have been checked, click on the  button or use  in the Task Bar.



This box is displayed :
Click on the **Export LparDesign Config to zPCR Basic study file** button.


Then and according to your CPU Model this information box is displayed:

Export LparDesign Config to zPCR Study file	
zPCR Version	9.4
Machine Type selected	8561-718
Hardware Model	Max71
z/OS Version for each LPAR	z/OS-2.3
Workload Type for each LPAR	User Defined
zAAP Loading %	0
zIIP Loading %	100
zIIP SMT Enabled and %	25
IFL SMT Enabled and %	25
VM Version for each LPAR	z/VM-7.1
VM Workload Type for each LPAR	Average
Select Export File	Cancel

Note: In certain situations, you might have to properly set the actual Hardware Model.



A field is displayed where you can select how you will process the setting of your workload characterisation: If you select “User Defined” the export will take what you have set in the CONFIG spreadsheet. Otherwise, you can choose a workload characterisation in the list:




In this case, **all the workload will have this characterisation** set in the zPCR study file.

You have to select these useful informations to create a proper zPCR Basic study File:


- The Hardware Model
- The z/OS or zVM version
- The workload type
- The zIIP Loading %

Then you have to select the name of the zPCR study file.


By default, we propose the current LPARDesign file name with a suffix of .zpcr as shown below:



You can select the folder and the file name. Then select SAVE and you will receive this message box specifying your choices:




10.4 Using the zPCR IMPORT feature.

Click on the  button or use **zPCR Menu** in the Task Bar.


This box is displayed :

Click on the **Import LparDesign Config from zPCR Basic study file** button.

The Windows file selection appears and select your zPCR Basic study file:



Click Open and your zPCR Basic Study File will be uploaded in the LPARDesign spreadsheet.
A message box will appear to show you file selection:



You are now in LPARDesign again and have to run all the appropriate function to validate your configuration.

Note : As zPCR only take into account active LP, if you Export to zPCR a configuration and then Import from zPCR the preceding exported zPCR file you could see some differences in the number of LP per Lpar. So be careful.




11. PRINTING THE SHEETS.

The print parameters have been set for most of the sheets to provide a common layout.

You print the sheet in displaying it and selecting the **Print** button in the action bar.
Some sheets like **SINET** and **Tables** cannot be printed using this button.

When you hit the Print Button you will have the standard pop-up:




You can change the Printer Name, check the output using the Preview button or print directly the sheet.



12. FAQ, COMMON MISTAKES AND RELEASE RECOMMENDATIONS.

12.1 FAQ

Q1 - When I open the workbook, the GCP, zIIP or IFL VALIDATION is set to NO.



R1 – This is the standard behavior. The Config Validation must be done after an open (re-open) of the workbook, which is why these fields are forced to NO. This is for data consistency.

Q2 – I want to calculate the HiperDispatch® LP configuration for zIIP, but the tool says that the configuration does not support HiperDispatch® or the GCP configuration has not been verified.

R2 – When you have zIIPs, you must go first to the CONFIG spreadsheet, run the Config Validation and HiperDispatch® for GCP, and then go to the CONFIG-zXXP spreadsheet to be able to run the calculation.

version will include them, as information only – so that the Import / Export from/to zPCR will be easier.

Q3 – zPCR Version.

In the spreadsheet, the zPCR version is “hard coded”. But as soon as a new zPCR version is available, the spreadsheet is updated and uploaded on the WLM Web Site.

Q4 – I am not an IBM employee, so how am I informed that a new version of zPCR is available?

To have the latest version go to the following URL:

http://www-03.ibm.com/systems/z/os/zos/features/wlm/WLM_Further_Info_Tools.html


and click on the LPAR Design HyperLink.

Or send a mail to alain_maneville@fr.ibm.com

Q5 – When I open the spreadsheet I have security messages – how can I get rid of them?

This almost happens when you open a new version for the first time.

You might get the following message:



What you must do now is simple:

Click on the “click for more details” area.


You will get this other message:



Then click on “Edit Anyway”

You will have this VB error message:





Then click on “End”
Save the spreadsheet
Re open it and all should be fine now.



12.2 COMMON MISTAKES.

M1 – Do not delete the remaining rows in the CONFIG, CONFIG-IFL or CONFIG-ZXXP worksheets even if you have less than 30, 40, 60 or 85 LPARs (which is mostly the case). If you do so, it can generate error if a new calculation is required.

- You have the **DELETE LPAR** feature that will help you to properly delete unwanted LPARs.

M2 – Even if you do not have zIIP, set the number of LP to zero or let it blank or set the Weight to zero or let it blank and validate the configuration if you want to use the zPCR link. Otherwise you will get an error message.


M3 – Never delete a row in the spreadsheet.

They will be cleaned automatically and remember that you have now the **DELETE LPAR** feature.

M4 – Try to use a fresh copy of the spreadsheet – use the Create a Copy feature and/or the Save as feature.

M5 – If no zIIP are to be used, set 0 in the #zIIP in the START spreadsheet.

M6 – In the list of available machines, you might find generic names like “Systems z13s” or z13-4XX. Those are NOT machines that you can select, they are pointers in the list to help you find faster the machine you want. If you select these generic names, you will get this pop-up message:



- For **IFL only machines** with no GCP, select machine like z13-4**00**, zEC12-7**00**. “**00**” means NO GCP.

M7 – When I change the CPU Type / # of processors and so on nothing changes:

Starting with V9-T01, we have introduced an “action bar” that makes travelling in the sheets easier. So, after a change in the START sheet, **you must use one of the “travel” buttons (GCP, IFL, zIIP)** to go to the appropriate sheet. This will, under the cover, checks the changes you have made and modify (if checks are ok) the configuration. If you travel in just clicking in the sheet name (in the workbook), some changes might not be done.

M8 – Rounding

Sometimes, the rounding of the result of a division (e.g.: Weight/Total_Weight) then multiplied by another number might give potential wrong information.

This is sometimes the case when calculating the number of guaranteed Physical Proc.

These rare cases happen in the EXPERT sheet when calculating the new Weight of a recommendation.

In this case, send a mail to the support and we will figure out how we can fix this case.



12.3 RELEASE RECOMMENDATIONS:

R1 – Use the new navigation BAR to “walk” within the different worksheets. Use the actions buttons to validate the configuration, see the messages, see the EXPERT advices and the DASHBOARD layouts.

Note : the previous actions are not available in the CONFIG-MSU worksheet as they are not appropriate in the sheet.

Here is it again:



If you want to change the Configuration Go to Start – other Icons are fast access when you work in a specific PU type.


To read some spreadsheet easier, you can use the Minimize/Maximize button to “make room”. When in Minimize configuration, the BAR will only use this space:



13. RECOMMENDED USAGE WORKFLOW



To make the study as simple as possible and to minimize the manual data entries (like LPAR Name, Weight, #LP, Workload characterization), its is recommended to use this workflow:





END OF DOCUMENT - Lpardesign-HD-Zpcr-V11-T01_Userguide.Docx

