
LPARDesign Extended

USER'S GUIDE

Version V01-T01





Doc : LPARDesign-Extended-V01-T01_UserGuide.docx © 2020 Thierry Deleris - Alain Maneville

Updated: May 13th, 2020

Alain Maneville

Executive I/T Specialist, zChampion z Client Architect

France

Table Of Content

1.	P	PURPOSE OF THE DOCUMENT	2
2.	D	DISCLAIMER OF WARRANTIES:	2
3.	H	HOW TO GET THE PRODUCT – IMPORTANT NOTICE: (VOIR AVEC THIERRY)	3
	3.1 3.2	FROM THE IBM WLM WEB SITE (AS OF OCTOBER 2018)	3
4.	C	CHANGES IN THIS RELEASE	4
	4.	WHAT'S NEW IN V01T01	4
5.	T	THE NAVIGATION AND ACTION BAR.	5
	5.1	BAR FUNCTIONS.	5
6.	L	PARDESIGN EXTENDED WORKFLOW - CREATING A STUDY AND LOADING FILES.	6
	6.1 6.2 6.3 6.4	STEP-1: CREATE A NEW STUDY (INITIAL USAGE)	6 7
7.	L	PARDESIGN EXTENDED WORKFLOW - COMPARING CONFIGURATIONS	9
	7.1 7.2 7.3 7.4 7.5	IMPORTANT NOTES ON THE COMPARISON PROCESS: STEP-1: REVIEWING THE LOADED CONFIGURATIONS. STEP-2: COMPARING CONFIGURATIONS – ENHANCED DASHBOARD. STEP-3 – COMPARE THE CONFIGURATIONS BY LPAR NAMES AND PU TYPES (GCP, ZIIP, IFL, ICF). STEP-4 – THE SORT RULES.	9 9 10
8.	0	OTHER FEATURES.	12
	8.1 8.2 8.	SIMPLE DASHBOARD. ZPCR STUDY GENERATION. 2.2.1 zPCR study generation workflow.	12
	8.3	THE DATA BUTTON - Data HOUSEKEEPING	



1. PURPOSE OF THE DOCUMENT.

This document explains how to use the LPARDesign Extended Tool.

This tool helps in comparing various LPAR configurations that have been created by the LPARDesign Tool. It provides visual comparisons and can create a zPCR study including these various LPAR configurations.

2. **DISCLAIMER OF WARRANTIES:**

The following [enclosed] macro is sample code created by Thierry Deleris (BPCE-IT) and Alain Maneville (IBM France).

This sample macro is not part of any standard IBM product and is provided to you solely for assisting you in the PR/SM LPAR ® and HiperDispatch® Configuration.

The code is provided "AS IS", without warranty of any kind. Thierry Deleris and Alain Maneville shall not be liable for any damages arising out of your use of such sample code, even if you have been advised of the possibility of such damage


Support: Support will be provided on a "best effort" basis. Send the spreadsheet for an analysis to thierry.deleris@bpce-it.fr, and/or to alain maneville@fr.ibm.com



3. HOW TO GET THE PRODUCT - IMPORTANT NOTICE: (voir avec Thierry)

3.1 From the IBM WLM WEB Site (as of October 2018)

https://www.ibm.com/it-infrastructure/z/zos-workload-management



Download LPAR design tool (ZIP, 2,2 MB)

And click on


3.2 From Github

Due to a change in IBM's way of managing WEB sites, the product is now available on the GitHub Web site at the URL:

https://github.com/AlainManeville/z-OS-LPARDesign

You will get this page:

LPARDesign Tool - Helps in configuring your CPC for PR/SM and HiperDispatch



Then, Click on the LPAR Design Hyperlink for the spreadsheet AND the User's Guide to download them.



4. CHANGES IN THIS RELEASE.

4.1 What's new in V01T01

The V01-T01 is the first version of the product.

4.1.1 Support for LPARDesign V11-T01

The configuration .xml files created by LPARDesign V11-T01 are supported in this tool.

4.1.2 Support for zPCR 9.4


zPCR 9.4 is supported in this release



5. THE NAVIGATION AND ACTION BAR.

To make things simpler and easier, a navigation and action BAR is provided. It is available when you open the spreadsheet and stays until you close it. You can move it anywhere in the worksheets (you will do that when first opening the product).

5.1 BAR Functions.




Sliding the mouse pointer to one of the icons shows its function:





6. LPARDesign Extended Workflow - Creating a Study and loading files.


6.1 STEP-1: Create a New Study (initial usage)



This will create a fresh LPARDesign Extended Study.

Now you must LOAD LPARDesign configuration files (.xml Files) to further compare them.


6.2 STEP-2: LOAD LPARDesign Configuration Files





6.3 STEP-3: Refine LPARDesign Configuration Files with further information for zPCR.


For example, you might need to specify what is the **Max**nnn value for this z15-T01 machine. **This is for zPCR** configuration to be accurate.



At that time you have Loaded this LPARDesign xml file, you will receive a confirmation PopUp and you can see you loaded configuration in the main worksheet:



The Id and the Name are those that you have set in:



You will do that for every LPARDesign configuration .xml file that you want to further compare



6.4 Setting the LPARDesign Extend Study Id

At any time, you can set or change the "name" of the study:

LPARDesign Extended - Study Id: My First LPARDesign Extended Study



7. LPARDesign Extended Workflow – Comparing Configurations.

This is the main objective of the Tool.

In this situation, you have loaded various LPARDesign configuration .xml files and you want to compare these configurations.

7.1 Important Notes on the comparison process:


You will be able to compare **By LPAR Name** – which is the key of the comparison process. For example, if you compare two machines where all the LPAR Names are not present, the LPARDesign Extended Tool will search only the LPAR Names that are present in both machines.

7.2 STEP-1: Reviewing the loaded configurations



In the main worksheet you have all the previously loaded configurations So, you need to choose which of them you want to compare.

7.3 STEP-2: Comparing Configurations – Enhanced Dashboard




After pressing the Enhanced Dashboard button, you will get the main worksheet panel where you can choose the configurations (Id and PU Type) to compare:





7.4 STEP-3 – Compare the configurations by LPAR Names and PU Types (GCP, zIIP, IFL, ICF)


In this example, we compare the Dashboards from the M1 and M2 configurations for the GCP PU.



We can easily determine that the W014 LPAR has one more VH in configuration M2:



Others PU types can be compared too – Just scroll the PU Type button list:



Note: To better analyze the configurations, scroll to have the LPAR name you want to check just below the column titles.

7.5 STEP-4 - The Sort Rules.

In the Enhanced Dashboard you could use the Sort Rules Box for your study:



In details here is the box:





The sort rules are divided between **LPAR Name** and **Guaranteed number of Physical Processor** (« Guarant #PP ») keys.


- In the LPAR Name part of the Box, the first button is the Join/No Join button
 - When Join is selected this lets you build a Dashboard where the lines of the two configurations are joined on the LPAR Name.



- In this case the LPAR Name will necessary be the first order Key and the Guarant #PP the second Key
- When No Join is selected there is no join on the LPAR Name between the lines of the two
 configurations selected in the Dashboard.



- In this case you could select the Key order of your choice.
- For each of these keys you could build the sort order by selecting the first and the second key by clicking on the corresponding button to switch
 - O Example :



In this case the sort order is first (« 1 ») LPAR Name and second (« 2 ») Guarant #PP without any join on the LPAR Name.


o <u>Example</u>:

From the previous box clicking on the the «1» button in the LPAR Name key part will switch it to «2» and so the Gurant #PP key will switch to «1».



In this case the sort order is first (« 1 ») Guarant #PP and second (« 2 ») LPAR Name

- For each of these keys you could too select the sort order between **Ascending** and **Descending** thanks to the corresponding button.
 - o In the last example:



You could see that the LPAR Name will be sorted in Ascending order and the Guarant #PP will be sorted in Descending order



8. Other Features.

8.1 Simple Dashboard.


When you hit you will have a unique Dashboard display as you have in LPARDesign. This is done to figure out a single configuration.

8.2 zPCR study generation

Dashboard

In this Tool, you can have multiple configurations. So you can generate a zPCR study including those configurations (with the limitation of zPCR)


8.2.1 zPCR study generation workflow.



8.3 The DATA button -

This will show you the raw values of the configurations you have loaded in the study.





8.4 Housekeeping

There are various buttons that helps you:

Create (new)


Restore (Load)

Save

Add (.xml Configuration)


Delete (.xml Configuration

to keep you study useful.









END OF DOCUMENT - Lpardesign-Extended-V01-T01_Userguide.Docx

